


56" SQUARE QUILT - DESIGNED BY RACHEL SHELBURNE



ROAM SWEET HOME FABRIC COLLECTION BY KRIS LAMMERS





Assembling the Units

1. Layer a Fabric 2 triangle on top of a Fabric 3 triangle. Sew on the right edge as shown. Press toward the Fabric 3 triangle. Make 36 units.





2. Layer a Fabric 3 triangle on top of a Fabric 2 triangle. Sew on the right edge as shown. Press toward the Fabric 2 triangle. Make 36 units.






3. Layer a Fabric 5 triangle on top of a Fabric 4 triangle. Sew on the right edge as shown. Press toward the Fabric 4 triangle. Make 36 units.





4. Layer a Fabric 4 triangle on top of a Fabric 5. Sew on the right edge as shown. Press toward the Fabric 5 triangle. Make 36 units.





5. Sew Step 1 and Step 3 units together to make a square, matching and pinning the center intersection. Twist the center to pop a few threads so the seam allowances spin around the center. Make 36 units. At this point the squares should measure 4½" square.




6. Sew Step 2 and Step 4 units together to make a square, matching and pinning the seam intersection and pressing as before. Make 36 units.

At this point the squares should measure 4½" square.



7. Sew the Step 5 and 6 units together to make 36 larger units measuring $4\frac{1}{2}$ " x $8\frac{1}{2}$ ". Press the center seam open.



8. Layer a Fabric 6 triangle on top of a Fabric 7 triangle. Sew on the right edge of the triangle. Press toward Fabric 7. Repeat to make 8 pairs.






9. Sew the Step 8 triangles together into squares, matching and pinning the seam intersection. Twist the center to pop a few stitches so the seam allowance can spin around the center. Press. Make 4 units measuring 8½" square.



Assembling the Quilt Top

- 1. Arrange the small and large Fabric 9 setting triangles, the Step 7 units, the Fabric 1 squares, the large Step 9 units and the Fabric 8 squares in diagonal rows following the diagram (shown below Step 4).
- 2. Sew the units together in rows, pressing toward the setting triangles and the small and large squares. NOTE: The setting triangles will be larger than needed. Put any excess at the edge of the quilt for trimming later.



- 3. Match and pin the seam intersections when joining the rows. Press the seams all one direction. Add the corner triangles last.
- 4. Carefully trim the edges of the quilt, leaving at least ¼" seam allowance from the corners of the blocks.



Borders

- 1. Measure the quilt through the middle. Piece and trim two borders to this length. Sew to the top and bottom of the quilt. Press toward the borders.
- 2. Repeat this procedure for the sides of the quilt.

Finishing the Quilt

- 1. Layer, baste and quilt as desired.
- 2. Sew the binding strips together with diagonal seams pressed open. Fold the binding in half, wrong sides together and press to make a double binding. Sew to the quilt with a 3/8" seam allowance, mitering the corners.
- 3. Trim the excess batting and backing, then turn the binding to the back side of the quilt and stitch down by hand with matching thread.

FABRIC		CUTTING	FABRIC	CUTTING
	Fabric 1 MAS8220-K 2 yds	From Fabric 1, cut: Fussy-cut 9—8½" squares on the diagonal	Fabric 8 MAS8226-W 1/3 yd	From Fabric 8, cut: 2 — 4½" WOF strips, into: 12 — 4½" squares
	Fabric 2 MAS609-KK1 ½ yd	From each of Fabrics 2-5, cut: 6 — 2½" WOF strips, into: 72 — 2½" Companion Angle Triangles	Fabric 9 MAS8223-W	From Fabric 9, cut: 1 — 13" WOF strip, into: 2 — 13" squares cut twice diagonally 1 — 7" WOF strip, into: 3 — 7" squares cut twice diagonally 1 — 8" WOF strip, into: 2 — 8" squares cut once diagonally (for corner triangles)
	Fabric 3 MAS513-KK2 ½ yd		1 yd	
	Fabric 4 MAS8232-UW ½ yd		Fabric 10 MAS609-Q2 % yd	From Fabric 10, cut: 6 — 2½" WOF strips for border
	Fabric 5 MAS8227-Q ½ yd		Fabric 11 MAS8228-Q % yd	From Fabric 11, cut: 6 — 2½" WOF strips for binding
	Fabric 6 MAS8222-K ⅓ yd	From Fabrics 6 and 7, cut: 2 — 4½" WOF strips, into: 8 — 4½" Companion Angle Triangles	Backing MAS8221-K 31/3 yds	Suggested Tool (optional): Companion Angle™ by Wrights
7710	Fabric 7 MAS8223-Q ⅓ yd			10 mm man m m m m m m m m m m m m m m m m

